



TMS INTRAWEB COMPONENT PACK DEVELOPERS QUICK START GUIDE

Contents

Supported Delphi, C++Builder, IntraWeb and Browser versions	3
Installation	4
Uninstall any previous versions, trials or separate components	4
Unzip the TMS IntraWeb Component Pack ZIP file into a new folder	4
Install packages	4
Setting library paths	10
Installing online help	10
Installing the component pack in multiple development environments	10
Updates	11
Support	12
Website login	13
License agreement	15
TMS IntraWeb Component Pack single developer license	15
TMS IntraWeb Component Pack site license	15
Termination of license	17
Component overview	18

Supported Delphi, C++Builder, IntraWeb and browser versions

The TMS IntraWeb Component Pack Pro supports following development environments:

Borland Delphi 7 (Professional, Enterprise, Architect)
Borland Delphi 2006 (Professional, Enterprise, Architect)
CodeGear Delphi 2007 (Professional, Enterprise)
CodeGear Delphi 2009 (Professional, Enterprise)
Embarcadero Delphi 2010 (Professional, Enterprise)
Embarcadero Delphi XE (Professional, Enterprise)
Embarcadero Delphi XE2 (Professional, Enterprise)
Embarcadero Delphi XE3 (Professional, Enterprise)

Borland C++Builder 2006 (Professional, Enterprise, Architect)
CodeGear C++Builder 2007 (Professional, Enterprise)
CodeGear C++Builder 2009 (Professional, Enterprise)
Embarcadero C++Builder 2010 (Professional, Enterprise)
Embarcadero C++Builder XE (Professional, Enterprise)
Embarcadero C++Builder XE2 (Professional, Enterprise)
Embarcadero C++Builder XE3 (Professional, Enterprise)

The TMS IntraWeb Component Pack Pro supports following IntraWeb versions:

IntraWeb 9.0 or higher
IntraWeb 10.0 or higher
IntraWeb 11.0 or higher
IntraWeb 12.0 or higher
IntraWeb 12.1 or higher
IntraWeb 14.0 or higher

The TMS IntraWeb Component Pack Pro can be simultaneously installed and used on multiple development environments on a single machine.

The TMS IntraWeb Component Pack Pro minimum browser version requirements:

Internet Explorer 5.5
Firefox 1.0 *
Opera 8 *
Chrome 4 *
Safari 5 *

* Some features gracefully degrade on some browsers such as gradients, only supported on Internet Explorer

The TMS IntraWeb Component Pack Pro is compatible with the HTML 5 document mode for all browsers listed above that support this mode.

Installation

Uninstall any previous versions, trials or separate components

Make sure to first uninstall any possible previous version of the TMS IntraWeb Component Pack or any component part of the TMS IntraWeb Component Pack that might have been separately installed. A correct uninstall means:

- Remove the package through Component, Install packages ..., Remove
- Delete ALL component DCU, OBJ, HPP, PAS, BPL, DCP, BPI files. Notice that .BPL, .DCP or .BPI files could have been generated in different directories!
- Remove the path from the library path via Tools, Environment options, Library, Library path

(additional frequently asked questions and answers can be found at
<http://www.tmssoftware.com/tmsiwaq.htm>

Unzip the TMS IntraWeb Component Pack ZIP file into a new folder

Install packages

In Delphi or C++Builder select from the menu File, Open and browse for the appropriate package files. After opening the package file, press Install from the package editor. Install the packages ONLY in the sequency as indicated:

For IntraWeb 9.0.x

Copy the file TMSDEFS9.INC to TMSDEFS.INC first !

Delphi 7 : IW9TMSD7.DPK
Delphi 7 : IW9TMSDED7.DPK
Delphi 7 : IW9TMSGRIDD7.DPK
Delphi 7 : IW9TMSGRIDDED7.DPK
Delphi 7 : IW9TMSXLSD7.DPK
Delphi 7 : IW9TMSSEDD7.DPK (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2006 : IW9TMSD2006.bdsproj
Delphi 2006 : IW9TMSDED2006.bdsproj
Delphi 2006 : IW9TMSGRIDD2006.bdsproj
Delphi 2006 : IW9TMSGRIDDED2006.bdsproj
Delphi 2006 : IW9TMSXLSD2006.bdsproj
Delphi 2006 : IW9TMSSEDD2006.bdsproj (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2007 : IW9TMSD2007.dproj
Delphi 2007 : IW9TMSDED2007.dproj
Delphi 2007 : IW9TMSGRIDD2007.dproj
Delphi 2007 : IW9TMSGRIDDED2007.dproj
Delphi 2007 : IW9TMSXLSD2007.dproj
Delphi 2007 : IW9TMSSEDD2007.dproj (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2006 : IW9TMS2006.BDSPROJ
C++Builder 2006 : IW9TMSDEC2006.BDSPROJ
C++Builder 2006 : IW9TMSGRIDC2006.BDSPROJ
C++Builder 2006 : IW9TMSGRIDDEC2006.BDSPROJ
C++Builder 2006 : IW9TMSXLSC2006.BDSPROJ
C++Builder 2006 : IW9TMSSEDC2006.BDSPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2007 : IW9TMS2007.CBPROJ
C++Builder 2007 : IW9TMSDEC2007.CBPROJ
C++Builder 2007 : IW9TMSGRIDC2007.CBPROJ
C++Builder 2007 : IW9TMSGRIDDEC2007.CBPROJ
C++Builder 2007 : IW9TMSXLSC2007.CBPROJ
C++Builder 2007 : IW9TMSSEDC2007.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

For IntraWeb 10.0.x

Copy the file TMSDEFS10.INC to TMSDEFS.INC first !

Delphi 7 : IW10TMSD7.DPK
Delphi 7 : IW10TMSDED7.DPK
Delphi 7 : IW10TMSGRID7.DPK
Delphi 7 : IW10TMSGRIDDED7.DPK
Delphi 7 : IW10TMSXLSD7.DPK
Delphi 7 : IW10TMSSEDD7.DPK (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2006 : IW10TMSD2006.bdsproj
Delphi 2006 : IW10TMSDED2006.bdsproj
Delphi 2006 : IW10TMSGRID2006.bdsproj
Delphi 2006 : IW10TMSGRIDDED2006.bdsproj
Delphi 2006 : IW10TMSXLSD2006.bdsproj
Delphi 2006 : IW10TMSSEDD2006.bdsproj (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2007 : IW10TMSD2007.dproj
Delphi 2007 : IW10TMSDED2007.dproj
Delphi 2007 : IW10TMSGRID2007.dproj
Delphi 2007 : IW10TMSGRIDDED2007.dproj
Delphi 2007 : IW10TMSXLSD2007.dproj
Delphi 2007 : IW10TMSSEDD2007.dproj (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2009 : IW10TMSD2009.DPROJ
Delphi 2009 : IW10TMSDED2009.DPROJ
Delphi 2009 : IW10TMSGRID2009.DPROJ
Delphi 2009 : IW10TMSGRIDDED2009.DPROJ
Delphi 2009 : IW10TMSXLSD2009.DPROJ
Delphi 2009 : IW10TMSSEDD2009.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2010 : IW10TMSD2010.DPROJ
Delphi 2010 : IW10TMSDED2010.DPROJ
Delphi 2010 : IW10TMSGRID2010.DPROJ
Delphi 2010 : IW10TMSGRIDDED2010.DPROJ
Delphi 2010 : IW10TMSXLSD2010.DPROJ
Delphi 2010 : IW10TMSSEDD2010.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 6 : IW10TMSC6.BPK
 C++Builder 6 : IW10TMSDEC6.BPK
 C++Builder 6 : IW10TMSGRIDC6.BPK
 C++Builder 6 : IW10TMSGRIDDEC6.BPK
 C++Builder 6 : IW10TMSXLSC6.BPK
 C++Builder 6 : IW10TMSSEDC6.BPK (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2006 : IW10TMSC2006.BDSProj
 C++Builder 2006 : IW10TMSDEC2006.BDSProj
 C++Builder 2006 : IW10TMSGRIDC2006.BDSProj
 C++Builder 2006 : IW10TMSGRIDDEC2006.BDSProj
 C++Builder 2006 : IW10TMSXLSC2006.BDSProj
 C++Builder 2006 : IW10TMSSEDC2006.BDSProj (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2007 : IW10TMSC2007.CBProj
 C++Builder 2007 : IW10TMSDEC2007.CBProj
 C++Builder 2007 : IW10TMSGRIDC2007.CBProj
 C++Builder 2007 : IW10TMSGRIDDEC2007.CBProj
 C++Builder 2007 : IW10TMSXLSC2007.CBProj
 C++Builder 2007 : IW10TMSSEDC2007.CBProj (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2009 : IW10TMSC2009.CBProj
 C++Builder 2009 : IW10TMSDEC2009.CBProj
 C++Builder 2009 : IW10TMSGRIDC2009.CBProj
 C++Builder 2009 : IW10TMSGRIDDEC2009.CBProj
 C++Builder 2009 : IW10TMSXLSC2009.CBProj
 C++Builder 2009 : IW10TMSSEDC2009.CBProj (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2010 : IW10TMSC2010.CBProj
 C++Builder 2010 : IW10TMSDEC2010.CBProj
 C++Builder 2010 : IW10TMSGRIDC2010.CBProj
 C++Builder 2010 : IW10TMSGRIDDEC2010.CBProj
 C++Builder 2010 : IW10TMSXLSC2010.CBProj
 C++Builder 2010 : IW10TMSSEDC2010.CBProj (only in TMS IntraWeb Component Pack Pro SE version)

For IntraWeb 11.0.x

Copy the file TMSDEFS11.INC to TMSDEFS.INC first !

Delphi 7 : IW11TMSD7.DPK
 Delphi 7 : IW11TMSDED7.DPK
 Delphi 7 : IW11TMSGRID7.DPK
 Delphi 7 : IW11TMSGRIDDED7.DPK
 Delphi 7 : IW11TMSXLS7.DPK
 Delphi 7 : IW11TMSSEDD7.DPK (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2006 : IW11TMSD2006.bdsproj
 Delphi 2006 : IW11TMSDED2006.bdsproj

Delphi 2006 : IW11TMSGRIDD2006.bdsproj
Delphi 2006 : IW11TMSGRIDDED2006.bdsproj
Delphi 2006 : IW11TMSXLS2006.bdsproj
Delphi 2006 : IW11TMSSEDD2006.bdsproj (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2007 : IW11TMSD2007.dproj
Delphi 2007 : IW11TMSDED2007.dproj
Delphi 2007 : IW11TMSGRIDD2007.dproj
Delphi 2007 : IW11TMSGRIDDED2007.dproj
Delphi 2007 : IW11TMSXLS2007.dproj
Delphi 2007 : IW11TMSSEDD2007.dproj (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2009 : IW11TMSD2009.DPROJ
Delphi 2009 : IW11TMSDED2009.DPROJ
Delphi 2009 : IW11TMSGRIDD2009.DPROJ
Delphi 2009 : IW11TMSGRIDDED2009.DPROJ
Delphi 2009 : IW11TMSXLS2009.DPROJ
Delphi 2009 : IW11TMSSEDD2009.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2010 : IW11TMSD2010.DPROJ
Delphi 2010 : IW11TMSDED2010.DPROJ
Delphi 2010 : IW11TMSGRIDD2010.DPROJ
Delphi 2010 : IW11TMSGRIDDED2010.DPROJ
Delphi 2010 : IW11TMSXLS2010.DPROJ
Delphi 2010 : IW11TMSSEDD2010.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2010 : IW11TMSD2010.DPROJ
Delphi 2010 : IW11TMSDED2010.DPROJ
Delphi 2010 : IW11TMSGRIDD2010.DPROJ
Delphi 2010 : IW11TMSGRIDDED2010.DPROJ
Delphi 2010 : IW11TMSXLS2010.DPROJ
Delphi 2010 : IW11TMSSEDD2010.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi XE : IW11TMSD2011.DPROJ
Delphi XE : IW11TMSDED2011.DPROJ
Delphi XE : IW11TMSGRIDD2011.DPROJ
Delphi XE : IW11TMSGRIDDED2011.DPROJ
Delphi XE : IW11TMSXLS2011.DPROJ
Delphi XE : IW11TMSSEDD2011.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2006 : IW11TMSC2006.BDSPROJ
C++Builder 2006 : IW11TMSDEC2006.BDSPROJ
C++Builder 2006 : IW11TMSGRIDC2006.BDSPROJ
C++Builder 2006 : IW11TMSGRIDDEC2006.BDSPROJ
C++Builder 2006 : IW11TMSXLS2006.BDSPROJ
C++Builder 2006 : IW11TMSSEDC2006.BDSPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2007 : IW11TMSC2007.CBPROJ
C++Builder 2007 : IW11TMSDEC2007.CBPROJ
C++Builder 2007 : IW11TMSGRIDC2007.CBPROJ
C++Builder 2007 : IW11TMSGRIDDEC2007.CBPROJ
C++Builder 2007 : IW11TMSXLS2007.CBPROJ
C++Builder 2007 : IW11TMSSEDC2007.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2009 : IW11TMS2009.CBPROJ
 C++Builder 2009 : IW11TMSDEC2009.CBPROJ
 C++Builder 2009 : IW11TMSGRIDC2009.CBPROJ
 C++Builder 2009 : IW11TMSGRIDDEC2009.CBPROJ
 C++Builder 2009 : IW11TMSXLSC2009.CBPROJ
 C++Builder 2009 : IW11TMSSEDC2009.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2010 : IW11TMS2010.CBPROJ
 C++Builder 2010 : IW11TMSDEC2010.CBPROJ
 C++Builder 2010 : IW11TMSGRIDC2010.CBPROJ
 C++Builder 2010 : IW11TMSGRIDDEC2010.CBPROJ
 C++Builder 2010 : IW11TMSXLSC2010.CBPROJ
 C++Builder 2010 : IW11TMSSEDC2010.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder XE : IW11TMS2011.CBPROJ
 C++Builder XE : IW11TMSDEC2011.CBPROJ
 C++Builder XE : IW11TMSGRIDC2011.CBPROJ
 C++Builder XE : IW11TMSGRIDDEC2011.CBPROJ
 C++Builder XE : IW11TMSXLSC2011.CBPROJ
 C++Builder XE : IW11TMSSEDC2011.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

For IntraWeb 12.x

For IntraWeb 12.0.x:

Copy the file TMSDEFS12.INC to TMSDEFS.INC first !

For IntraWeb 12.1.x:

Copy the file TMSDEFS121.INC to TMSDEFS.INC first !

Delphi 2009 : IW12TMSD2009.DPROJ
 Delphi 2009 : IW12TMSDED2009.DPROJ
 Delphi 2009 : IW12TMSGRIDD2009.DPROJ
 Delphi 2009 : IW12TMSGRIDDED2009.DPROJ
 Delphi 2009 : IW12TMSXLSD2009.DPROJ
 Delphi 2009 : IW12TMSSEDD2009.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2010 : IW12TMSD2010.DPROJ
 Delphi 2010 : IW12TMSDED2010.DPROJ
 Delphi 2010 : IW12TMSGRIDD2010.DPROJ
 Delphi 2010 : IW12TMSGRIDDED2010.DPROJ
 Delphi 2010 : IW12TMSXLSD2010.DPROJ
 Delphi 2010 : IW12TMSSEDD2010.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi 2010 : IW12TMSD2010.DPROJ
 Delphi 2010 : IW12TMSDED2010.DPROJ
 Delphi 2010 : IW12TMSGRIDD2010.DPROJ
 Delphi 2010 : IW12TMSGRIDDED2010.DPROJ
 Delphi 2010 : IW12TMSXLSD2010.DPROJ
 Delphi 2010 : IW12TMSSEDD2010.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi XE : IW12TMSD2011.DPROJ
 Delphi XE : IW12TMSDED2011.DPROJ
 Delphi XE : IW12TMSGRIIDD2011.DPROJ
 Delphi XE : IW12TMSGRIIDDED2011.DPROJ
 Delphi XE : IW12TMSXLS2011.DPROJ
 Delphi XE : IW12TMSSEDD2011.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Delphi XE2 : IW12TMSDXE2.DPROJ
 Delphi XE2 : IW12TMSDEDXE2.DPROJ
 Delphi XE2 : IW12TMSGRIIDXE2.DPROJ
 Delphi XE2 : IW12TMSGRIIDDEDXE2.DPROJ
 Delphi XE2 : IW12TMSXLSXE2.DPROJ
 Delphi XE2 : IW12TMSSEDDXE2.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2009 : IW12TMSC2009.CBPROJ
 C++Builder 2009 : IW12TMSDEC2009.CBPROJ
 C++Builder 2009 : IW12TMSGRIDC2009.CBPROJ
 C++Builder 2009 : IW12TMSGRIDDEC2009.CBPROJ
 C++Builder 2009 : IW12TMSXLS2009.CBPROJ
 C++Builder 2009 : IW12TMSSEDC2009.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder 2010 : IW12TMSC2010.CBPROJ
 C++Builder 2010 : IW12TMSDEC2010.CBPROJ
 C++Builder 2010 : IW12TMSGRIDC2010.CBPROJ
 C++Builder 2010 : IW12TMSGRIDDEC2010.CBPROJ
 C++Builder 2010 : IW12TMSXLS2010.CBPROJ
 C++Builder 2010 : IW12TMSSEDC2010.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder XE : IW12TMSC2011.CBPROJ
 C++Builder XE : IW12TMSDEC2011.CBPROJ
 C++Builder XE : IW12TMSGRIDC2011.CBPROJ
 C++Builder XE : IW12TMSGRIDDEC2011.CBPROJ
 C++Builder XE : IW12TMSXLS2011.CBPROJ
 C++Builder XE : IW12TMSSEDC2011.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder XE2 : IW12TMSCXE2.CBPROJ
 C++Builder XE2 : IW12TMSDECXE2.CBPROJ
 C++Builder XE2 : IW12TMSGRIDCXE2.CBPROJ
 C++Builder XE2 : IW12TMSGRIDDECXE2.CBPROJ
 C++Builder XE2 : IW12TMSXLSXE2.CBPROJ
 C++Builder XE2 : IW12TMSSEDCXE2.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

For IntraWeb 14.x

Copy the file TMSDEFS140.INC to TMSDEFS.INC first !

Delphi XE3 : IW14TMSDXE3.DPROJ
 Delphi XE3 : IW14TMSDEDXE3.DPROJ
 Delphi XE3 : IW14TMSGRIIDXE3.DPROJ
 Delphi XE3 : IW14TMSGRIIDDEDXE3.DPROJ
 Delphi XE3 : IW14TMSXLSXE3.DPROJ
 Delphi XE3 : IW14TMSSEDDXE3.DPROJ (only in TMS IntraWeb Component Pack Pro SE version)

C++Builder XE3 : IW12TMSCXE3.CBPROJ
 C++Builder XE3 : IW12TMSDECXE3.CBPROJ
 C++Builder XE3 : IW12TMSGRIDCXE3.CBPROJ
 C++Builder XE3 : IW12TMSGRIDDECXE3.CBPROJ
 C++Builder XE3 : IW12TMSXLSCXE3.CBPROJ
 C++Builder XE3 : IW12TMSSEDCXE3.CBPROJ (only in TMS IntraWeb Component Pack Pro SE version)

Setting library paths

Under Tools, Environment Options, Library, Library path, add the directory where the TMS components have been installed to the library path.

Installing online help

For Delphi 7 it is required to first put the IWTMS.ALS file in the {\$DELPHI}\Help directory BEFORE installing the help files in the IDE.

Go through menu Help, Customize and add following file to the Index tab:

Delphi 7 : IWTMSD7.HLP

for Delphi 2006,2007,2009 & C++Builder 2006,2007,2009,2010,XE:

Delphi 2006 : execute RegHelp2.exe /I iwptmsdBDS4W.hxx
 Delphi 2007 : execute RegHelp2.exe /I iwptmsdBDS5W.hxx
 Delphi 2009 : execute RegHelp2.exe /I iwptmsdRS2009W.hxx
 Delphi 2010 : execute RegHelp2.exe /I iwptmsdRS2010W.hxx
 Delphi XE : execute RegHelp2.exe /I iwptmsdRSXE.hxx

C++Builder 2006 : execute RegHelp2.exe /I iwptmsbBDS4W.hxx
 C++Builder 2007 : execute RegHelp2.exe /I iwptmsbBDS5W.hxx
 C++Builder 2009 : execute RegHelp2.exe /I iwptmsbRS2009W.hxx
 C++Builder 2010 : execute RegHelp2.exe /I iwptmsbRS2010W.hxx
 C++Builder XE : execute RegHelp2.exe /I iwptmsbRSXE.hxx

Installing the component pack in multiple development environments

The recommended procedure to install the component pack in different Delphi or C++Builder environments on a single machine is to unzip the TMS IntraWeb Component Pack into a different folder for each Delphi or C++Builder version and to use as such a different library path for each Delphi or C++Builder version.

Updates

The TMS IntraWeb Component Pack Pro comes with a full version cycle of free updates. A full version cycle means that from version x.y to version x+1.y, the updates are free. For example, if a registration starts at version v2.5, updates are free till version v3.5 (ie. the last free version that will be received is v3.4). The updates for the TMS IntraWeb Component Pack are frequently made available. The latest date of the updates can be seen after login on our website (see next section). This date reflects the exact file date of the latest update.

Support

TMS IntraWeb Component Pack Pro registered users have priority support on the special email:
support@tmssoftware.com

For peer to peer support for registered users only, a newsgroup is available. Details about the newsgroup server and login can be found on the registered users page after login on our website.

Website login

Registered users of the TMS IntraWeb Component Pack Pro receive a code with which it is possible to login on the website to obtain:


- Free updates for a full version cycle of the components.
- Discount offers on other products
- Access to additional documentation
- Access to samples projects
- Change registration email
- Information for peer to peer support newsgroup access

Login on the website is done with:

- Email with which you registered the TMS IntraWeb Component Pack (Script Edition)
- Code that is sent by email with the first registered version

Direct link to login:

<http://www.tmssoftware.com/site/login.asp>



Important notes

Keep this email and code in a safe place.

If for some reason, your registration email address changes, the only way to have this updated is by sending email to TMS software to request for a change. The email **must** be sent from the original email address and specify the new address to change to. Email address changes are manually checked. If an email change is requested for a single developer license, changes to email addresses belonging to other persons will not be allowed.

Make sure to use an email account that can handle file attachments up to 1.5MB, that there is no filtering on ZIP attachments, contents of ZIP attachments and that there is no spam filter or other filters that would block the receipt of emails with updates.

License agreement

The TMS IntraWeb Component Pack is available with two licensing schemes, a single developer license and a site license. The details of the two license types are below:

TMS IntraWeb Component Pack single developer license

The license of the component gives you the right to:

- Using the component for development of applications or any type of software module in general by a single developer within the company holding the license.
- Sell any commercial compiled application with the control, published by the company holding the license.
- Make modifications to the source code of component for own use.
- Use the component and source code on all development systems used by the developer assigned by the company holding the license.
- Request future versions of the component at any time either through the web or by email for a full version cycle of the component or maximum 3 years after purchase. After expiry of the registration TMS software can no longer provide any old version of software, documentation or samples. TMS software is not a backup service and expects backups to be made by the licensed user.
- Access to priority email support by the single developer assigned by the company holding the license during the license period.
- Sell any number of applications in any quantity without any additional run-time fees required

The license agreement prevents you from:

- Distributing parts or full source code of any component from TMS software.
- Using parts or full source code of components from the TMS software for creating any type of other components that are distributed or sold with or without source code.
- Changing the source code of any component from TMS software and sell or distribute this as a modified product.
- Creating a descendant compiled product such as OCX or ActiveX control and sell or distribute this as a product
- Using the control in applications sold with different publisher name than the company holding the license
- Transfer the license to another developer
- Transfer the license to another company
- Using the components by multiple developers in the company holding the license
- The license agreement terminates immediately after violation of any of the terms and conditions described

TMS IntraWeb Component Pack site license

The site license of the component gives you the right to:

- Using the component for development of applications or any type of software module in general by any developer within the company holding the license.
- Sell any commercial compiled application with the control, published by the company holding the license
- Make modifications to the source code of component for own use.

- Use the component and source code on all development systems used by the developer assigned by the company holding the license.
- Request future versions of the component at any time either through the web or by email for a full version cycle of the component. Please keep a backup of the latest versions that you obtain. We can not guarantee that we can keep providing old versions after registration expiry.
-
- Access to priority email support by any developer assigned by the company holding the license.
- Sell any number of applications in any quantity without any additional run-time fees or royalties required.
- Change at any time the number of developers using the TMS software components within the company holding the license.
- Notify TMS software at any time to allow new developers within the company to access the priority email support.
- Allow any number of developers within the company holding the license to access the web based interface for obtaining product updates.

The site license agreement prevents you from:

- Distributing parts or full source code of any component from TMS software.
- Using parts or full source code of components from the TMS software for creating any type of other components that are distributed or sold with or without source code.
- Changing the source code of any component from TMS software and sell or distribute this as a modified product.
- Creating a descendant compiled product such as OCX or ActiveX control and sell or distribute this as a product.
- Using the control in applications sold with different publisher name than the company holding the license.
- Transfer the license to any other developer not working for the company holding the license.

Termination of license

The license agreement terminates immediately after violation of any of the terms and conditions described. A termination of the license means that the company has no longer any rights to use the components for development, sell applications using the components, obtain free updates of the components and is no longer entitled to email support or any other form of support.

The company or developer holding the license is responsible for respecting the terms and conditions of the license agreement and shall thus make sure that no other person has access to the TMS Components to use these for any purposes that violate the license agreement.

Component overview

TTIWHTMLLabel, TTIWDBHTMLLabel

Labels that allow using HTML formatting at design time

TTIWHTMLRadioGroup

Radiogroup with design time HTML formatting support

TTIWHTMLCheckBox

Checkbox with design time HTML support

TTIWHTMLList

List with design time HTML support

TTIWCalendar, TTIWDBCalendar

Monthcalendar controls with various options to control the appearance

TTIWDatePicker, TTIWDBDatePicker

Datepicker controls with various options to control the appearance

TTIWDateSelector

Date selector control with configurable selection of day,month,year

TTIWStaticMenu

Static menu with hover effect

TTIWAdvEdit, TTIWDBAdvEdit

Advanced edit control with various settings to restrict incorrect entries, set controls, keyboard handling

TTIWAdvLUEdit, TTIWDBAdvLUEdit

Advanced edit control with built-in type-ahead lookup capability

TTWEMailEdit

Edit control with regular expression validation for email

TTIWFilePicker

Edit control with attached file picker button

TTIWMainMenu, TTIWSideMenu

Dropdown menu controls

TTIWSideNavBar

XP style navigational control

TTIWExchangeBar

Outlook 2003 style navigational control

TTIWAdvImage

Image with library free design time GIF & JPEG support as well as hover image capability

TTIWFadeImage

Image with hover fade effect

TTIWHotSpotImage

Image with client-side ImageMap support for JPEG and GIF files with design time hot spot editor

TTIWPaintBox

Paintbox that renders in a browser allowing to draw on a canvas just like in a Win32 application

TTIWClock

Client side running clock

TTIWSmartPanel

Expanding / collapsing panel

TTIWScrollPanel

Scrolling panel

TTIWTickerPanel

Ticker with optional expanding/collapsing part

TTIWPersistentEdit

Edit control with cookie persistency

TTIWCountryComboBox

Combobox with all countries predefined

TTIWOutlookBar

Outlookbar control

TTIWColorPicker

Color picker control

TTIWAdvImageButton

Tri-state image based button control

TTIWPopupMenuButton

Button with attached popup menu

TTIWPopupMenuLabel

Label with attached popup menu

TTIWMonthCalendar

Month calendar that can show events or appointments with detail per day

TTIWCCNumEdit

Credit card number edit control with client side basic validation

TTIWCCExpEdit

Credit card expiry date edit control with client side basic validation

TTIWListLink, TTIWComboListLink, TTIWEditLinkLink

Client side listbox to listbox link, combobox to listbox link and edit to listbox link

TTIWHTMLEdit, TTIWDBHTMLEdit

Client side html editors with toolbar

TTIWAdvSpinEdit, TTIWDBAdvSpinEdit

Data-aware and not data-aware spin edit controls

TTIWAdvDateEdit, TTIWDBAdvDateEdit

Edit control for date entry

TTIWAdvTimeEdit, TTIWDBAdvTimeEdit

Edit control for time entry

TTIWCheckList

Edit control with dropdown checklist

TTIWClientCode

Container for clientside Javascript, clientside CSS

TTIWClientDebugOut

Interface to component for sending OutputDebugString from Javascript

TTIWRadioButton

Single radiobutton control

TTIWScrollBarColors

Component for controlling browser scrollbar color (IE only)

TTIWScrollBarPersistence

Component for keeping the browser scroll position persistent across multiple page views

TTIWAdvWebGrid

Highly configurable and feature packed non data-aware grid control

TTIWDBAdvWebGrid

Highly configurable and feature packed data-aware grid control

TTIWAdvDetailWebGrid

Design time grid configuration control for use in detail row of master grid

TTIWDBAdvDetailWebGrid

Design time DB-aware grid configuration control for use in detail row of master DB-aware grid

TTIWAUTOFormFill

Component to cache & preset multiple controls at once client-side

TTIWAdvRadioGroup

Radiogroup control with with async events and async rendering capabilities

TTIWAdvCheckGroup

Checkboxgroup control with with async events and async rendering capabilities

TTIWAdvTreeView

Highly configurable treeview component with async events and async rendering capabilities

TTIWAdvMessageDialog

Highly configurable modal dialog component with async events and async rendering capabilities

TTIWDBAsyncNavigator

Database navigator with full async support

TTIWContinuousScroll

Continuous scroll control with full async support to add extra items to a list when scrolling, pressing a button or programmatically